


How to use the HACCP Visualizer tool


I. Device selection:

As the contents of the HACCP files are different for the RATIONAL cooking systems, a separate graphical user interface has been developed for each device type.

- For example, click on the hyperlink: "[→ iCombi Pro/ iHexagon](#)"



- If a device type is selected, the view will change automatically:



If the user wants to return to the 'Device selection' menu item to select a different device type, click on the '[Back to device selection](#)' hyperlink.

II. Open and analyze the HACCP file:

All types of HACCP files can be analyzed using this tool:

- Offline data: Loaded directly from the device via USB:
 - *haccp.txt* (multiple batches in one file).
- Online data: The HACCP data provided with the Data Download Tool can be loaded and visualized with the tool:
 - *haccp.txt* (each batch/program in a file).
 - *haccp.xml* files (each batch/program in a file).

Welcome to the Data Download Tool!

Serial Number:

From: To:

Data Types: ☐ infolog ☒ haccp ☐ service ☐ report


Please note:

- infolog data newer than 2025-05-26 is not yet available.
- Some data might not yet be transferred if the device is offline (see last known online date below).
- infolog, haccp and service data are transferred differently. Therefore differences in data availability are possible.
- Data of RATIONAL Lab units is not transferred to SDP-Data Lake.
- Tips regarding data quality could be wrong for lab units.


1. Offline data:

a. File upload:



- Press the "Open and Analyse HACCP file" button.



- A pop-up message is displayed in which you can either drag & drop the file or select it by pressing the [browse files](#) option (as shown in the figure below).
- You can then press the "Open file" button so that the file can be loaded.



- If an invalid file is loaded, a pop-up message appears prompting the user to open a correct file with the correct tool. In addition, the HACCP file content indicator element is marked with the “X” symbol.



- In a good case, the content of the HACCP file is loaded and displayed as follows:

Open and Analyse HACCP-File Back to device selection **RATIONAL**

General | Distribution of processes over time | Details of the selected programme | Graphic Display of single selected processes | Compare cleaning processes | Graphic Display of two selected cleaning processes

Specifications:

Information	Details
Device type	E101
Serial number	E115J22092996035
Software versions (from/till)	LM100-16.3.4 / LM100-16.3.15
Timeline (from/till)	2023.02.20 08:51:21 / 2023.03.30 10:36:51

Press the button to display details:
Charge Nr: 91

Default View ☒ Sort Process name HACCP File Content: ☒

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☒	91	Cleaning	Light without steam generator descaling (auto dose)	2023.02.20 08:51:21	007:44:39	Completed	73.15
☐	92	Cleaning	Medium without steam generator descaling (auto dose)	2023.02.20 16:36:08	016:27:16	Completed	62.04
☐	93	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.21 09:03:41	004:13:48	Completed	44.72
☐	94	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.21 13:23:59	002:13:06	Completed	49.12
☐	95	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.21 15:46:07	023:10:02	Completed	36.39
☐	96	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.22 15:31:32	000:15:46	Completed	58.29
☐	97	Cleaning	Rinse without tabs (auto dose)	2023.02.22 15:49:42	000:00:12	Cancelled/aborted	36.00
☐	98	Cleaning	Emergency clean	2023.02.22 15:49:55	000:00:02	Cancelled/aborted	36.00
☐	99	Cleaning	Rinse without steam generator descaling (auto dose)	2023.02.22 16:15:02	021:49:41	Completed	59.71
☐	100	IPM	IPM	2023.02.23 14:30:39	000:00:24	Cancelled/aborted	25.00
☐	101	Cooking process	Manual Cooking Mode	2023.02.23 16:03:16	000:00:02	Cancelled/aborted	25.00
☐	102	Cooking process	Manual Cooking Mode	2023.02.23 16:08:08	000:00:02	Cancelled/aborted	25.00
☐	103	Cooking process	Manual Cooking Mode	2023.02.23 16:08:56	000:00:06	Cancelled/aborted	25.00
☐	104	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.23 16:11:48	000:52:36	Completed	54.17
☐	105	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.27 07:36:59	000:19:15	Completed	56.70
☐	106	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.27 08:01:07	000:35:20	Completed	64.36
☐	107	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.27 08:36:35	000:00:46	Cancelled/aborted	36.00
☐	108	Cleaning	Emergency clean	2023.02.27 08:37:22	000:00:02	Cancelled/aborted	34.00
☐	109	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2023.02.27 08:37:31	000:04:17	Cancelled/aborted	29.75
☐	110	Cleaning	Emergency clean	2023.02.27 08:41:49	000:00:02	Cancelled/aborted	28.00
☐	111	Cleaning	Light without steam generator descaling (auto dose)	2023.02.27 09:11:48	000:00:11	Cancelled/aborted	32.00
☐	112	Cleaning	Emergency clean	2023.02.27 09:12:00	000:00:02	Cancelled/aborted	32.00

b. Data visualization:

• General:

The general information is displayed on the first tab. The 'Specifications' table shows the necessary and current information about the device.

The second table contains the most important information on each program/recipe. A few features have been added to this table to make it more user-friendly:

• Feature search:

- If you are searching for a specific term, you can enter the desired text in the first line of each column --> Only the matching texts are displayed.

Open and Analyse HACCP-File Back to device selection **RATIONAL**

General | Distribution of processes over time | Details of the selected programme | Graphic Display of single selected processes | Compare cleaning processes | Graphic Display of two selected cleaning processes

Specifications:

Information	Details
Device type	E61T
Serial number	E61T124073155446
Software versions (from/till)	LM100-17.3.14 / WA45manual_100_4 / LM100-17.3.14 / WA45manual_100_4
Timeline (from/till)	2024.11.06 08:28:42 / 2024.12.06 12:48:52

Press the button to display details:
Charge Nr 54

Default View ☒ Sort Process name HACCP File Content: ☒

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☐	64	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.07 13:23:34	000:36:45	Completed	59.22
☐	75	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.18 12:46:11	000:47:42	Completed	60.63
☐	76	Cleaning	Light eco without steam generator descaling (auto dose)	2024.11.18 13:34:10	002:15:39	Completed	58.29
☐	92	Cleaning	Light eco with steam generator descaling (auto dose)	2024.11.20 10:49:44	007:07:06	Completed	49.87
☐	150	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.28 10:19:06	000:17:54	Completed	74.79
☐	160	Cleaning	Light eco without steam generator descaling (auto dose)	2024.11.28 16:47:01	002:16:46	Completed	58.70
☐	228	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.12.04 15:31:02	000:17:25	Completed	64.83

You can also enter texts in several columns at the same time:

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☐	76	clean	Lig	2024.11.18 13:34:10	002:15:39	Completed	58.29
☐	160	Cleaning	Light eco without steam generator descaling (auto dose)	2024.11.28 16:47:01	002:16:46	Completed	58.70

- Press the 'Sort Process name' button if you want to sort the tables by process name (arrow up or down):

Default View ☐ Sort Process name HACCP File Content: ☒

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☐	150	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.28 10:19:06	000:17:54	Completed	74.79
☐	160	Cleaning	Light eco without steam generator descaling (auto dose)	2024.11.28 16:47:01	002:16:46	Completed	58.70
☐	228	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.12.04 15:31:02	000:17:25	Completed	64.83
☐	64	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.07 13:23:34	000:36:45	Completed	59.22
☐	75	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.18 12:46:11	000:47:42	Completed	60.63
☐	76	Cleaning	Light eco without steam generator descaling (auto dose)	2024.11.18 13:34:10	002:15:39	Completed	58.29
☐	92	Cleaning	Light eco with steam generator descaling (auto dose)	2024.11.20 10:49:44	007:07:06	Completed	49.87
☐	103	Cooking process	Finishing a la carte panfry	2024.11.25 14:53:25	000:00:44	Cancelled/aborted	218.00
☐	105	Cooking process	Finishing a la carte panfry	2024.11.25 15:14:06	000:01:19	Cancelled/aborted	203.00
☐	106	Cooking process	Manual Cooking Mode	2024.11.25 15:15:29	000:05:38	Cancelled/aborted	110.77
☐	107	Cooking process	Finishing a la carte panfry	2024.11.25 15:21:25	000:01:41	Cancelled/aborted	41.00
☐	110	Cooking process	Finishing a la carte panfry	2024.11.25 15:39:20	000:00:12	Cancelled/aborted	196.50
☐	111	Cooking process	Finishing a la carte panfry	2024.11.25 15:40:00	000:00:58	Cancelled/aborted	193.50
☐	114	Cooking process	Finishing a la carte grilling	2024.11.25 17:15:48	000:00:29	Cancelled/aborted	105.00
☐	115	Cooking process	Finishing a la carte baking	2024.11.25 17:16:25	000:00:23	Cancelled/aborted	101.00
☐	116	Cooking process	Finishing a la carte sauté	2024.11.25 17:16:55	000:00:22	Cancelled/aborted	100.50
☐	117	Cooking process	Finishing a la carte grilling	2024.11.25 17:17:24	000:00:15	Cancelled/aborted	99.00
☐	118	Cooking process	Finishing a la carte grilling	2024.11.25 17:20:36	000:00:51	Cancelled/aborted	87.50
☐	119	Cooking process	Finishing a la carte grilling	2024.11.25 17:22:00	000:03:08	Cancelled/aborted	81.00
☐	120	Cooking process	Baking Products Pizza	2024.11.26 09:44:35	000:00:07	Cancelled/aborted	23.00

- Default View: Press the 'Default view' check mark if you want to reset the table view to the standard view.

Default View ☒ Sort Process name HACCP File Content: ☒

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☒	54	Cooking process	Manual Cooking Mode	2024.11.06 08:28:42	000:06:15	Cancelled/aborted	44.30
☐	55	Cooking process	Unknown	2024.11.06 08:35:33	000:02:04	Cancelled/aborted	69.75
☐	56	Cooking process	Unknown	2024.11.06 08:40:38	000:15:56	Cancelled/aborted	66.11
☐	57	IPM	IPM	2024.11.07 09:09:41	000:00:24	Cancelled/aborted	21.00
☐	58	Cooking process	Finishing a la carte panfry	2024.11.07 09:10:16	000:00:32	Cancelled/aborted	21.00
☐	59	IPM	IPM	2024.11.07 09:10:49	000:04:37	Cancelled/aborted	21.00
☐	60	Cooking process	Finishing a la carte panfry	2024.11.07 09:15:35	000:13:28	Completed	200.57
☐	61	Cooking process	Finishing a la carte panfry	2024.11.07 12:28:02	000:16:31	Completed	170.62
☐	62	IPM	IPM	2024.11.07 12:44:40	000:29:10	Cancelled/aborted	229.94
☐	63	Cooking process	Manual Cooking Mode	2024.11.07 13:13:53	000:09:29	Cancelled/aborted	115.47
☐	64	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.07 13:23:34	000:36:45	Completed	59.22

- Select a program and display details:

To view the details of a specific program/recipe, select it in the first column of the General tab and then press the button at the top right "Press the button to display details". The content of the button is updated automatically (charge number).

Specifications:

Information	Details
Device type	E61T
Serial number	E61TJ24073155446
Software versions (from/till)	LM100-17.3.14 / WA45manual_100_4 / LM100-17.3.14 / WA45manual_100_4
Timeline (from/till)	2024.11.06 08:28:42 / 2024.12.06 12:48:52

Default View: ☒ HACCP File Content: ☒

Sort Process name

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☐	64	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.07 13:23:34	000:36:45	Completed	59.22
☐	75	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.18 12:46:11	000:47:42	Completed	60.63
☒	76	Cleaning	Light eco without steam generator descaling (auto dose)	2024.11.18 13:34:10	002:15:39	Completed	58.29
☐	92	Cleaning	Light eco with steam generator descaling (auto dose)	2024.11.20 10:49:44	007:07:06	Completed	49.87
☐	150	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.11.28 10:19:06	000:17:54	Completed	74.79
☐	160	Cleaning	Light eco without steam generator descaling (auto dose)	2024.11.28 16:47:01	002:16:46	Completed	58.70
☐	228	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2024.12.04 15:31:02	000:17:25	Completed	64.83

After you have pressed the button, the view automatically switches to the third tab, 'Details of the selected programme'.

- Details of the selected programme:

The individual details are displayed here. These are the details of the selected recipe.

For each event/mode, the measured temperatures, the unit used, and their time stamp are displayed in tabular form.

Important information can be seen/find, for example for Auto-Dose appliances: It is displayed whether the amount of care/cleaning fluid is sufficient or not.

Open and Analyse HACCP-File Back to device selection **RATIONAL**

General | Distribution of processes over time | Details of the selected programme | Graphic Display of single selected processes | Compare cleaning processes | Graphic Display of two selected cleaning processes

Details of the selected programme:

Information	Detail
Charge Nr.:	76
Programme Id.:	592
Software version:	LM100-17.3.14 / WA45manual_100_4
Start date and time:	2024.11.18 13:34:10
Process type:	Cleaning
Programme name:	Light eco without steam generator descaling (auto dose)

Mode/Event	Cooking cabinet temp.	Core probe Setpoint temp.	Core sensor actual temp.	Date and Time
Door closed	55 C	-	60 C	Monday, November 18, 2024 3:40:09 PM
Door closed	55 C	-	46 C	Monday, November 18, 2024 3:41:09 PM
Door closed	51 C	-	45 C	Monday, November 18, 2024 3:42:09 PM
Door closed	48 C	-	49 C	Monday, November 18, 2024 3:43:09 PM
Door closed	46 C	-	47 C	Monday, November 18, 2024 3:44:09 PM
Door closed	44 C	-	45 C	Monday, November 18, 2024 3:45:09 PM
Door closed	43 C	-	44 C	Monday, November 18, 2024 3:46:09 PM
Door closed	42 C	-	42 C	Monday, November 18, 2024 3:47:09 PM
Door closed	41 C	-	42 C	Monday, November 18, 2024 3:48:09 PM
Door closed	40 C	-	41 C	Monday, November 18, 2024 3:49:09 PM
Door closed	40 C	-	41 C	Monday, November 18, 2024 3:49:49 PM
Cleaning finished, Sufficient detergent amount 1(1yes 0no). Sufficient care amount: 1(1yes 0no)	40 C	-	41 C	Monday, November 18, 2024 3:49:49 PM
Program finished with back button	40 C	-	41 C	Monday, November 18, 2024 3:49:49 PM

For "iHexagon" Devices, it also shows whether the microwaves were active or broken.

Mode/Event	Cooking cabinet temp.	Core probe Setpoint temp.	Core sensor actual temp.	Date and Time
Door closed	64 C	-	64 C	Wednesday, November 6, 2024 8:42:38 AM
Door closed	67 C	-	67 C	Wednesday, November 6, 2024 8:45:38 AM
Door closed	64 C	-	67 C	Wednesday, November 6, 2024 8:46:38 AM
Door closed	66 C	-	69 C	Wednesday, November 6, 2024 8:47:38 AM
Door closed	66 C	-	68 C	Wednesday, November 6, 2024 8:48:38 AM
Door closed	65 C	-	68 C	Wednesday, November 6, 2024 8:49:38 AM
Door closed	65 C	-	66 C	Wednesday, November 6, 2024 8:50:38 AM
Door closed	65 C	-	65 C	Wednesday, November 6, 2024 8:51:38 AM
Door closed	66 C	-	65 C	Wednesday, November 6, 2024 8:52:38 AM
Door closed	66 C	-	65 C	Wednesday, November 6, 2024 8:56:24 AM
Door opened	66 C	-	65 C	Wednesday, November 6, 2024 8:56:24 AM
Microwave = Used: 1 Broken: 0	63 C	-	64 C	Wednesday, November 6, 2024 8:56:34 AM
Program was aborted	63 C	-	64 C	Wednesday, November 6, 2024 8:56:34 AM

If cleaning errors occur in the **iCombi Classic HACCP file**) an error history has been implemented. This function helps the user to identify the recipe in which an error first occurred.

- Cleaning errors for iCombi Classic:

If the LED display "Cleaning error found?" LED indicator shows red, this means that a cleaning error has occurred --> **All recipes that come after a cleaning error show this LED indicator red. Recipes before the cleaning error don't light red.** This makes it easy for the user to find out in which recipe the error occurred first.

Cleaning errors can be checked in the "Program details" table in the "Mode/event" section.
Error events are also displayed in red.

Open and Analyse HACCP-File

Back to device selection

RATIONAL

General | Distribution of processes over time | Details of the selected programme | Graphic Display of single selected processes | Compare cleaning processes | Graphic Display of two selected cleaning processes

Details of the selected programme:

Information	Detail
Charge Nr.:	3451
Process name	Cleaning programme without descaling process
Programme name	Heavy cleaning
Start date and time:	14.03.22 / 20:50:03
Duration:	02:37:43
Status:	Completed
Average temperature:	66.65

Cleaning error found? ●

(!) This indicates that an error is present. It may be related to this recipe or it may have occurred earlier.

Mode/Event	Cabinet temp. target (°C/°F)	Cabinet temp. (°C/°F)	Core temp. target (°C/°F)	Core temp. (°C/°F)	Date and Time
CLEAN STEP 001	0	70	---	63	14.03.22 / 20:53:22
CLEAN STEP 002	0	70	---	63	14.03.22 / 20:53:22
Door closed	0	70	---	63	14.03.22 / 20:53:22
CLEAN STEP 003	0	70	---	63	14.03.22 / 20:53:46
CLEAN STEP 004	0	70	---	63	14.03.22 / 20:53:57
Mode STEAM	0	70	---	63	14.03.22 / 20:53:57
Mode STEAM	30	77	---	65	14.03.22 / 20:54:02
CLEAN STEP 009	30	77	---	65	14.03.22 / 20:54:09
CLEAN STEP 010	30	77	---	65	14.03.22 / 20:54:18
CLEAN STEP 011	30	77	---	65	14.03.22 / 20:54:30
CLEAN STEP 012	30	77	---	65	14.03.22 / 20:54:37
CLEAN STEP 013	30	77	---	65	14.03.22 / 20:54:44

(!) Scroll through the table to find the error, if it exists.

The user can also sort the contents of this table by clicking on each column header. This can simplify searching for a service error, for example:

Open and Analyse HACCP-File

Back to device selection

RATIONAL

General | Distribution of processes over time | Details of the selected programme | Graphic Display of single selected processes | Compare cleaning processes | Graphic Display of two selected cleaning processes

Details of the selected programme:

Information	Detail
Charge Nr.:	3074
Process name	Cleaning programme without descaling process
Programme name	Heavy cleaning
Start date and time:	28.02.22 / 21:29:14
Duration:	00:04:40
Status:	Completed
Average temperature:	84.33


Cleaning error found? ●

Click on each column header to sort information

Mode/Event	Cabinet temp. target (°C/°F)	Cabinet temp. (°C/°F)	Core temp. target (°C/°F)	Core temp. (°C/°F)	Date and Time
CLEAN ABORT	30	78	---	63	28.02.22 / 21:32:13
CLEAN ABORT	30	83	---	70	28.02.22 / 21:33:12
CLEAN ERROR 010	30	78	---	63	28.02.22 / 21:32:13
CLEAN START PROG 002	---	---	---	---	28.02.22 / 21:29:14 ---
CLEAN STEP 001	0	71	---	61	28.02.22 / 21:31:25
CLEAN STEP 002	0	71	---	61	28.02.22 / 21:31:25
Door closed	0	71	---	61	28.02.22 / 21:31:25
Door closed	30	78	---	63	28.02.22 / 21:32:12
Door closed	30	83	---	70	28.02.22 / 21:33:32
Door opened	---	---	---	---	28.02.22 / 21:29:17 ---
Door opened	30	83	---	70	28.02.22 / 21:33:25
Door opened	30	83	---	70	28.02.22 / 21:33:38

- Graphic Display of single selected processes:

For better visualization the measured temperatures of individual recipes and door openings are also displayed graphically. This allows unexpected temperature values to be detected quickly and how often are doors opened during a recipe.



- Graphic feature:
 - ❖ Cursor legend:


To display the exact measured values with their time stamp, place the cursor at the bottom of the diagram. The cursor is displayed in the diagram at the point where the selected point with the coordinates (x, y) is located. If the user activates/presses the magnet symbol "🧲", they can only navigate between the measuring points. Selecting the symbol "📏" allows free navigation in the graph. User can display multiple cursors on a graph.



❖ Plot Legend:


Defines the color and style of plots. Customizing the plots that appear in the plot area of a graph helps distinguish each plot from another. Use the plot legend to customize how each plot appears in the plot area of a graph. Click a glyph in the plot legend and select from the following options in the shortcut menu to customize how the plot appears in the plot area of a graph:


- Line Style: Provides solid and dashed line styles.
- Line Width: Provides line widths.
- Color: Displays the color picker so the user can select the color of the plot.
- No line: Specifies that the representation as a line in the diagram is not displayed.
- Show value on hover: Display value with mouse pointer (values are in integer format).



❖ Graph tool:

Use the graphic tool to customize the display. Press the '🔍' symbol to display a specific section only. Select the part you want to display in the graphic, as shown in the image below:






Press the “” symbol if you want to display the complete graph again.


- **Distribution of processes over time:**

If the user wants to have an overview of the use of the device, they can find this under the corresponding tab.

The first graph shows an overview of the recipes used over time.



The diagram settings function allows the user to customize the view as desired:



➔ As the above image illustrates, the user maintains a high level of hygiene with regular cleaning of the device.

There are also two tables under this tab:

- General statistics: shows the number of each process.
 - Cleaning statistics show whether cleaning was carried out in standard or eco mode, or aborted for “iCombi Pro” devices. They also show whether cleaning was carried out with or without descaling, and whether cleaning was aborted for “iCombi Classic” devices.
- ➔ Aborted cleanings refer to cleanings where errors occurred (not the emergency clean!).

General statistics:		Cleaning statistics:			
Process	quantity	Cleaning name	Without descaling process	With descaling process	Aborted cleaning
Cooking processes	481	Express	0	0	0
Cleaning programme with descaling process	4	Light	0	2	0
Cleaning programme without descaling process	26	Medium	0	0	0
Total days	28	Strong	4	24	1

For the “iVario” devices, the number of operating modes used is shown individually or in combination.

General statistics:	
Operating mode	Quantity
FRYING	23
BOILING	6
Mixed: (FRYING; BOILING; PRESSURE)	0
Mixed: (FRYING; BOILING)	3
Mixed: (BOILING; PRESSURE)	0
Mixed: (FRYING; PRESSURE)	0
Total days	3

- **Compare cleaning processes:**

As cleaning processes in good case have standardized procedures, users can compare **two cleanings of the same type**.

This method enables users to quickly identify where deviations or errors have occurred (This can be, for example, a drop or jump in temperature that occurs unexpectedly).

If the selected cleanings are of the same type, the display will show 'Same programme type?' in green.

In this case, the user can press the button displaying the selected charge number.

Open and Analyse HACCP-File

Back to device selection

RATIONAL

General Distribution of processes over time Details of the selected programme Graphic Display of single selected processes Compare cleaning processes Graphic Display of two selected cleaning processes

Press the button to display the graphic of the two selected cleaning processes

Charge Nr: 241; 314 same programme type ?

1

2

5

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☒	241	Cleaning	Strong eco with steam generator descaling (auto dose)	2025.01.11 22:34:31	003:51:15	Completed	71.01
☐	247	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.12 22:22:27	002:56:56	Completed	67.91
☐	255	Cleaning	Light eco without steam generator descaling (auto dose)	2025.01.13 20:23:37	002:19:15	Completed	69.51
☐	264	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2025.01.15 09:10:13	000:17:04	Completed	68.33
☐	273	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.15 20:23:15	002:53:58	Completed	67.37
☐	281	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.16 21:07:29	003:10:08	Completed	77.90
☐	288	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.17 21:01:03	002:57:21	Completed	68.36
☐	292	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.18 22:09:40	002:57:11	Completed	64.03
☐	295	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.19 20:41:41	002:56:21	Completed	65.76
☐	306	Cleaning	Strong eco without steam generator descaling (auto dose)	2025.01.20 21:53:32	003:35:57	Completed	71.27
☒	314	Cleaning	Strong eco with steam generator descaling (auto dose)	2025.01.21 21:30:54	004:01:18	Completed	68.39
☐	321	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.22 21:36:03	003:01:23	Completed	66.24
☐	327	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.23 22:47:01	008:21:43	Cancelled/aborted	84.32
☐	328	Cleaning	Emergency clean	2025.01.24 07:08:45	000:00:02	Cancelled/aborted	79.00
☐	332	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.25 00:53:15	003:03:59	Completed	68.20
☐	337	Cleaning	Strong eco without steam generator descaling (auto dose)	2025.01.25 23:01:44	003:37:23	Completed	70.62
☐	342	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.26 20:15:10	003:03:30	Completed	63.90
☐	350	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.27 21:12:44	002:53:46	Completed	65.56
☐	356	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.28 21:30:34	002:53:22	Completed	64.16
☐	363	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.30 21:45:29	002:55:34	Completed	66.92
☐	372	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.31 22:24:26	002:58:20	Completed	71.71
☐	378	Cleaning	Strong eco without steam generator descaling (auto dose)	2025.02.01 21:40:57	003:36:04	Completed	72.22
☐	382	Cleaning	Medium eco with steam generator descaling (auto dose)	2025.02.02 20:42:32	003:12:30	Completed	62.30
☐	386	Cleaning	Strong eco without steam generator descaling (auto dose)	2025.02.03 21:22:00	003:33:51	Completed	74.21
☐	392	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.02.04 21:54:48	002:57:18	Completed	69.89
☐	401	Cleaning	Strong eco without steam generator descaling (auto dose)	2025.02.05 21:13:02	003:32:51	Completed	73.12

➔ In this case, the last tab, "Graphic display of two selected cleaning processes," will be automatically displayed.

If the user attempts to compare three cleaning processes, a message is displayed indicating that only two cleaning processes can be compared:

Open and Analyse HACCP-File

Back to device selection

RATIONAL

General Distribution of processes over time Details of the selected programme Graphic Display of single selected processes Compare cleaning processes Graphic Display of two selected cleaning processes

Press the button to display the graphic of the two selected cleaning processes

Charge Nr: 241; 314 same programme type ?


You cannot select more than two programmes!

OK

Selected	Charge Nr.	Process name	Programme name	Date and time	Duration	Status	Average temp. (°C/°F)
☒	241	Cleaning	Strong eco with steam generator descaling (auto dose)	2025.01.11 22:34:31	003:51:15	Completed	71.01
☐	247	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.12 22:22:27	002:56:56	Completed	67.91
☐	255	Cleaning	Light eco without steam generator descaling (auto dose)	2025.01.13 20:23:37	002:19:15	Completed	69.51
☐	264	Cleaning	Interim cleaning without steam generator descaling (auto dose)	2025.01.15 09:10:13	000:17:04	Completed	68.33
☐	273	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.15 20:23:15	002:53:58	Completed	67.37
☒	281	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.16 21:07:29	003:10:08	Completed	77.90
☐	288	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.17 21:01:03	002:57:21	Completed	68.36
☐	292	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.18 22:09:40	002:57:11	Completed	64.03
☐	295	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.19 20:41:41	002:56:21	Completed	65.76
☐	306	Cleaning	Strong eco without steam generator descaling (auto dose)	2025.01.20 21:53:32	003:35:57	Completed	71.27
☒	314	Cleaning	Strong eco with steam generator descaling (auto dose)	2025.01.21 21:30:54	004:01:18	Completed	68.39
☐	321	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.22 21:36:03	003:01:23	Completed	66.24
☐	327	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.23 22:47:01	008:21:43	Cancelled/aborted	84.32
☐	328	Cleaning	Emergency clean	2025.01.24 07:08:45	000:00:02	Cancelled/aborted	79.00
☐	332	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.25 00:53:15	003:03:59	Completed	68.20
☐	337	Cleaning	Strong eco without steam generator descaling (auto dose)	2025.01.25 23:01:44	003:37:23	Completed	70.62
☐	342	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.26 20:15:10	003:03:30	Completed	63.90
☐	350	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.27 21:12:44	002:53:46	Completed	65.56
☐	356	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.28 21:30:34	002:53:22	Completed	64.16
☐	363	Cleaning	Medium eco without steam generator descaling (auto dose)	2025.01.30 21:45:29	002:55:34	Completed	66.92


The user can therefore either select or deselect a cleaning process.

If the user attempts to compare even two cleanings of different types, a message is displayed stating that this is not possible:



- Graphic Display of two selected cleaning processes:

The measured temperatures and door openings over time for the two selected cleaning types are shown here:




2. Online data:

Online data (HACCP txt and xml files) loaded using the Download tool can also be analyzed using this tool.

--> As each existing batch/recipe is stored in a separate HACCP file for online files, the graphical user interface differs from that of offline HACCP files:

The image below illustrates where information from a recipe is displayed.



- Further Notes/Questions?

If you have any further notes, questions or something else do not hesitate to contact us by using the "Feedback" Button:

Welcome to the RTS DaViD (Data Visualization and Download-Tool)!

Target: DaViD is intended to offer RATIONAL employees the best possible support for their troubleshooting tasks. To this end, it is consolidating all the tools for analyzing the data from RATIONAL cooking systems. It provides access to all device data of networked cooking systems and offers analysis options for these online as well as offline cooking systems.

Tools:

Data Download Enables the download of all device data from networked cooking systems (infoLog, HACCP, service)

HACCP – Visualizer Allows the upload and graphical display of HACCP.txt/xml files (iCP, iHexagon, iCC, iVP)

Service File – Visualizer Allows you to upload and easily display deviations in the service.xml files (iCP, iHexagon, iVP)

We value your feedback

[Feedback](#)